Installing the software

Download the Mixly_WIN.7z archive, right-click and decompress it to your local disk. See the online folder:

http://yourduino.com/docs/MIXLY/

It also has the 7Z decompression software for both 32 and 64 bit Windows. You need to install that to decompress / install the first part of MIXLY.


The following is a translation of the page on mixly.org:

annotation

最新版Mixly.txt

- It is recommended to decompress to the root directory of the hard disk.
 like c:\ The path cannot contain Chinese and special characters (such as: _(), etc.).
- Recommended installation path such as C: \Mixly

The directory after extraction is shown in the figure.



The first decompression software contains only the most basic files and cannot be run directly.

You need to run one-click update.bat or update.bat to download the latest version of Mixly software. This will take a LONG time..

After waiting a moment, the update progress is displayed.

```
D:\Mixly_WIN\
Mixly_Upgrading, Please wait...
HEAD is now at 0785255 restart git commit
remote: Enumerating objects: 29024, done.
remote: Counting objects: 100% (29024/29024), done.
remote: Compressing objects: 100% (18281/18281), done.
remote: Total 29024 (delta 9671), reused 28373 (delta 9221)
Receiving objects: 100% (29024/29024), 628.85 MiB | 19.27 MiB/s, done.
Resolving deltas: 100% (9671/9671), done.
From https://gitee.com/mixlyplus/Mixly
* branch master -> FETCH_HEAD
0785255b..bc94c90e master -> origin/master
Updating files: 29% (6561/22622)
```

Eventually you will see the prompt "Mixly Update Complete", the software download is complete.

Mixly 升级助手

```
D:\Mix1y_WIN\
```

```
D:\Mixly WIN>echo Mixly 正在升级中,请等待...
Mixly 正在升级中,请等待...
HEAD is now at bc94c90e 1.0.8Beta2
From https://gitee.com/mixlyplus/Mixly
* branch master -> FETCH_HEAD
Already up to date.
系统找不到指定的文件。
Enumerating objects: 29030, done.
Counting objects: 100% (29030/29030), done.
Delta compression using up to 12 threads
Compressing objects: 100% (17834/17834), done.
Writing objects: 100% (29030/29030), done.
Total 29030 (delta 9674), reused 29030 (delta 9674)

D:\Mixly_WIN\PortableGit\cmd>echo Mixly更新完成,Enjoy it!
Mixly更新完成,Enjoy it!
请按任意键继续...
```

After the update is complete, the software directory is shown in the figure.

You can double-click Mixly.exe to open the Mixly software.

